

<SERVERDATA>\easa\admin\config\context.properties

context.properties

```
# Usage - Custom properties file for the EASA webapp.
#
# Add here properties to override the default ones
#

# Location for resources used with file choice object SERVER location
# filechoice.server.folder=

# To print current mode in corner of the screen
#show.mode.indicator=true
#easa.db.port=9001
#easa.db.name=easa

# Uncomment this line to enable easa to use remote jsf servers. By
# default a local one will be used
#easa.jsf.remote=true

# Replacement will leave the whole line empty the dor does not exists,
# and this is set.
# Otherwise only the missing dor will be replaced with empty string.
#easa.server.replacement.compatible=4.3.3

#the default load balancer algorithm is excelandopeningtimes
#easa.jsf.load balancer.algorithm=excelandmemory
#easa.jsf.load balancer.algorithm=excelandopeningtimes
#easa.jsf.load balancer.algorithm=openingtimes
#easa.jsf.load balancer.algorithm=excel

# this property adjusts the weight of opening times in case of "excel
# and opening times algorithm".
# Default is 1.0 which means equal balance. bigger number means opening
# times are more important.
#easa.jsf.load balancer.weight.multiplier=1.0

#Time server checks if there is something to delete. default: 1hr
#easa.server.deleteoldsims.loop.wait.millis=
#Easa will auto-delete sim folders after given number of days. Default
#is: Never
#easa.server.deleteoldsims.threshold.days=30

# Use the old dependency calculation algorithm - default is true (use
# the old one)
#easa.client.dependency.information.old.alg=false
```

```
# Output advanced debugging information about the dependency
calculation to the log [0-7]
#easa.client.dependency.debug.level=4

# Esaps listed here will be preloaded by jsf servers.
#preloaded.easap.ids.1=examples/tutorial_mort_calc2

# Easaps where global dependencies are needed
#global.dependencies.easap.ids.1=examples/tutorial_mort_calc2

#The preloader can be limited to use only some of the free excel
processes to preload easaps.
# Default is 30, but it can be configured to use any value between 1
and 100.
#percentage.of.free.excel.to.be.used.for.preloader=30

# url for connection from web browser to easa server, if easa server is
on a remote machine
#easa.server.public=http://127.0.0.1/easa

# url for connection to easa server for intra-server communication
#easa.server.private=http://127.0.0.1/easa
```